

# **OpenText™ IMaaS Tools for VS Code**

## **User Guide**

This guide describes how to use the OpenText™ IMaaS Tools VS Code extension pack for developing and deploying applications that consume the OpenText™ IMaaS APIs.

**This documentation has been created for software version OpenText™ IMaaS Tools for VS Code 22.2.6 User Guide.**

It is also valid for subsequent software releases unless OpenText has made newer documentation available with the product, on an OpenText website, or by any other means.

**Open Text Corporation**

275 Frank Tompa Drive, Waterloo, Ontario, Canada, N2L 0A1

Tel: +1-519-888-7111

Toll Free Canada/USA: 1-800-499-6544 | International: +800-4996-5440

Fax: +1-519-888-0677

Support: <https://support.opentext.com>

For more information, visit <http://www.opentext.com>

**Copyright © 2022 Open Text. All Rights Reserved.**

Trademarks owned by Open Text.

One or more patents may cover this product. For more information, please visit <https://www.opentext.com/patents>

**Disclaimer**

No Warranties and Limitation of Liability

Every effort has been made to ensure the accuracy of the features and techniques presented in this publication. However, Open Text Corporation and its affiliates accept no responsibility and offer no warranty whether expressed or implied, for the accuracy of this publication.

Last updated: 06/14/2022

# Contents

<b>1</b>	<b>Introduction .....</b>	<b>3</b>
<b>2</b>	<b>Overview .....</b>	<b>4</b>
2.1	OpenText IMaaS Tools view .....	4
2.2	Explorer view .....	5
2.3	Command Palette .....	6
<b>3</b>	<b>Setting up an authentication profile.....</b>	<b>7</b>
<b>4</b>	<b>Setting up a project.....</b>	<b>9</b>
<b>5</b>	<b>Creating models .....</b>	<b>11</b>
5.1	Creating a namespace .....	13
5.2	Creating a trait definition.....	14
5.3	Creating a type definition .....	16
5.4	Creating a workflow model .....	19
<b>6</b>	<b>Deploying a project.....</b>	<b>20</b>
<b>7</b>	<b>Using the otcloud Command Line Interface.....</b>	<b>22</b>
<b>8</b>	<b>Contact information .....</b>	<b>23</b>


# 1 Introduction

This user guide provides instructions for pro-code developers on how to use the OpenText™ IMaaS Tools for VS Code 22.2.6 to build applications that consume the IMaaS (Information Management as a Service) APIs from the OpenText™ API Cloud.

It covers the topics of connecting to a developer organization in the API Cloud, creating an IMaaS application project with its different models (IMaaS application configuration artifacts), and deploying this application to the different IMaaS APIs through the integrated ALM (Application Lifecycle Management) deployment functionality.


We recommend that you always use the link to this user guide from the OpenText™ IMaaS Tools **Help and Feedback** section in VS Code (see Fig. 1.1), so that you are certain to have the up-to-date user guide which corresponds with the IMaaS Tools for VS Code version you have installed in your Microsoft VS Code IDE.

Fig. 1.1:



In addition to this user guide, the **Help and Feedback** section also contains the IMaaS developer tutorial (see Fig. 1.2), which guides you through a detailed journey on how to build an application with the OpenText™ IMaaS Tools for VS Code. It is highly recommended you follow this tutorial as a way of getting started, as not only will it provide you with a thorough understanding of the use of the IMaaS functionality in VS Code, but it will also explain where to find key developer documentation, and how to consume the IMaaS APIs of the OpenText™ API Cloud.

Fig. 1.2:



## 2 Overview

Installing the OpenText™ IMaaS Tools VS Code extension pack adds the IMaaS developer functionality to the Microsoft Visual Studio Code IDE.

The IMaaS developer functionality is available in VS Code from three different locations:


- The **OpenText IMaaS Tools** view in the VS Code Activity Bar
- The **Explorer** view in the VS Code Activity Bar
- The VS Code **Command Palette**

In this chapter we will go over these three locations and describe the IMaaS developer capabilities they provide.

### 2.1 OpenText IMaaS Tools view


In VS Code, you can switch between different views through the Activity Bar (see Fig. 2.1).

Fig. 2.1:



When the OpenText™ IMaaS Tools VS Code extension pack is installed, you can access the OpenText IMaaS Tools view from the Activity Bar (see Fig 2.2).

Fig. 2.2:




The OpenText IMaaS Tools view is divided into three sections:

- **Organizations:**  
This is where the developer can configure the authentication profile to allow connecting and deploying to a developer organization in the OpenText™ API Cloud.
- **Models:**  
This is where the developer can configure the OpenText project and, once configured, explore the different models that exist in the project.
- **Help and Feedback:**  
This is where the developer can directly access the OpenText™ IMaaS Tools VS Code extension pack's user guide, the IMaaS developer tutorial (explains how to get started with developing IMaaS applications), and where they can report an issue or suggest a new feature.

## 2.2 Explorer view

In the standard VS Code Explorer view, installing the OpenText™ IMaaS Tools VS Code extension pack adds two menu entries to the contextual menu of the VS Code workspace root folder (see Fig. 2.3).

Fig. 2.3:




- Clicking the **OpenText: Project Properties** menu entry opens the IMaaS project properties screen, allowing you to edit the project and application properties.
- Clicking the **OpenText: Deploy Project** menu entry deploys your IMaaS application project to the configured OpenText™ API Cloud developer organization.

## 2.3 Command Palette

The VS Code Command Palette (available by pressing **Ctrl+Shift+P** or **F1**, depending on your system) allows you to access all the functionality of VS Code. So, the functionality that has been added to VS Code by the OpenText™ IMaaS Tools VS Code extension pack is also directly available from the Command Palette (see Fig. 2.4), i.e.: as the different commands.

Since the Command Palette allows filtering commands, typing “**opentext**” in the filter box will ensure you see all added OpenText™ IMaaS Tools related commands.

Fig. 2.4:



The commands from the Command Palette that allow creating new models will be described further in the [Creating models](#) chapter of this user guide.

You now have an understanding of the different locations in VS Code where you can access the features of the OpenText™ IMaaS Tools extension pack. The following chapters in this user guide describe how to use those features.

### 3 Setting up an authentication profile

This chapter describes how to set up your VS Code IMaaS authentication profile. More specifically, it details how to create a connection to your developer organization in the OpenText™ API Cloud, so that it is possible to use this connection later to deploy your application project to the API Cloud.

Adding a connection to an API Cloud developer organization is done by editing the authentication profile in the **OpenText Authentication Profile** configuration screen (see Fig. 3.2). It is accessible via the **Edit Profile** button under the **Organizations** section of the **OpenText IMaaS Tools** view (see Fig. 3.1).

Fig. 3.1:





Fig. 3.2:

The screenshot shows the 'OpenText Authentication Profile' configuration screen. It has a dark background with white text. The title 'OpenText Authentication Profile' is at the top. Below it are four labeled input fields: '\* Profile Name' with 'Default' entered, '\* Organization Name', '\* Organization ID', and '\* Public Client ID'. Each field has a white input box.

The different authentication profile properties on the **OpenText Authentication Profile** configuration screen are:


- **Profile Name:** the name of the authentication profile (defaulted to **Default**)
- **Organization Name:** the name of the developer organization
- **Organization ID:** the (unique) ID of the developer organization
- **Public Client ID:** the public client ID of the developer organization

Organization name, Organization ID and Public Client ID are provided when creating an organization in **developer.opentext.com**, and they can also be retrieved through the organization Console in your **developer.opentext.com** subscription.

To save the authentication profile configuration, select **Save** from the **File** menu, or press **Ctrl+S** on your keyboard.

To test the configured authentication profile, click **Connect** from the **Organizations** section in the **OpenText IMaaS Tools** view (see Fig. 3.3).

Fig. 3.3:



## 4 Setting up a project

This chapter describes how to set up a (IMaaS application) project. Setting up (i.e.: configuring) a new project is essential, as it enables the IMaaS developer modeling capabilities within the context of the current VS Code workspace folder. Without project configuration, you will not be able to create models for your IMaaS application project.

Setting up a project is done via the **Set Up Project** button under the **Models** section of the **OpenText IMaaS Tools** view (see Fig. 4.1). Note that this button is only available when a project has not yet been set up. When clicked, the **OpenText Project Properties** configuration screen opens (see Fig. 4.2).

Fig. 4.1:





Fig. 4.2:

A screenshot of the 'OpenText Project Properties' configuration window. The title bar says 'OpenText Project Properties'. The form contains the following fields:

- \* Project name: Input field with 'my\_imaas\_application' entered.
- \* Application display name: Empty input field.
- \* Application name: Empty input field.
- \* Application description: Empty text area.
- \* Application version: Input field with '1.0' entered.
- Application vendor: Empty input field.


The different project properties on the **OpenText Project Properties** configuration screen are:

- **Project name:** the name of the IMaaS application project; a default value is automatically filled using the VS Code workspace folder name (this can be different from the application name itself)
- **Application display name:** the user-friendly name (i.e.: label) of the IMaaS application
- **Application name:** the unique (technical) name of the IMaaS application; a default value is automatically filled using the (previously entered) application display name
- **Application description:** the description of the IMaaS application
- **Application version:** the version label of the IMaaS application, defaulted to "1.0"
- **Application vendor:** the name of the owner/vendor of the application

To save the project configuration, select **Save** from the **File** menu, or press **Ctrl+S** on your keyboard.

Once a project has been set up for the VS Code workspace (folder), the **Models** section shows the model tree instead of the **Set Up Project** button. The model tree allows exploring and editing the models that exist within the project (see Fig. 4.3).

Fig. 4.3:



When a project has been set up, you can always view or modify the OpenText project properties from the VS Code **Explorer** view by choosing **OpenText: Project Properties** from the contextual menu of your VS Code workspace (root) folder (see Fig. 4.4) or any of its subfolders, or by opening the **.otproject** file (see Fig. 4.5):

Fig. 4.4:





Fig. 4.5:



## 5 Creating models

This chapter describes how to create models. Models are the configuration artifacts that define your IMaaS application itself. Deploying an application effectively amounts to deploying the different models to their respective IMaaS API endpoints in the OpenText™ API Cloud.

For each type of model, the OpenText™ IMaaS Tools provide a bespoke editor or modeler. To create a new model and launch the corresponding modeler, there are three methods:


1. Through the  button (see Fig. 5.1.1) or the **New Model** menu entry of the [...] menu (see Fig. 5.1.2) of the **Model Explorer** (**Models** section of the **OpenText IMaaS Tools**).

Fig. 5.1.1:






Fig. 5.1.2:




This will allow you to select the type of model you want to create (see Fig. 5.1.3). You will be asked to provide a model name when clicking the chosen model type.

Fig. 5.1.3:



2. Through the **Command Palette** (see Fig. 5.2). You will be asked to provide a model name when choosing one of the commands. Note that you can either use the **OpenText: New Model** command (which will behave the same way as the previously explained method) or any of the commands for direct creation of specific types of models.


Fig. 5.2:



Note that it is only allowed to create models in a model folder (the **otresources** folder that was automatically generated when setting up the project, or one of its subfolders). This means that for the above two methods, you need to save the model inside the **otresources** folder.


3. From the **Explorer** view, through the **OpenText: New Model** menu entry (see Fig. 5.3.1) from the contextual menu on a model folder (i.e.: the **otresources** folder or one of its subfolders).

Fig. 5.3.1:



This will allow you to select the type of model you want to create (see Fig. 5.3.2). You will be asked to provide a model name when clicking the chosen model type.

Fig. 5.3.2:




The remainder of this chapter describes the different modelers and how to use them to create the corresponding models.

## 5.1 Creating a namespace

A namespace allows grouping the different types, traits, and workflows together (e.g.: within the context of an application). For more information on namespaces, you can refer to the [Define a namespace, trait and "FILE" document type](#) section in the Content Metadata Service (CMS) product documentation or the [Namespace](#) resource documentation in the Content Metadata Service API reference.

You can create a namespace via any of the three [model creation methods](#). This opens the namespace modeler (see Fig. 5.4).

Fig. 5.4:

The image shows a dark-themed user interface for creating a namespace. It features four input fields: 'Display name' with the value 'My Namespace', 'Name' with the value 'my\_namespace', 'Prefix' which is empty, and 'Description' which is a large empty text area. Each field has a small red asterisk icon to its left, indicating it is a required field.

The different model properties on the namespace modeler screen are:

- **Display name:** the user-friendly name (i.e.: label) of the namespace; this does not have to be unique, and a default value is automatically filled using the model name you initially chose
- **Name:** the (technical) name of the namespace; this has to be unique (within your developer tenant), and a default value is automatically filled using the display name
- **Prefix:** the prefix representing the namespace (used in system naming of traits and types that are within that namespace); this has to be unique (within your developer tenant)
- **Description:** the description of the namespace

To save the namespace model, select **Save** from the **File** menu, or press **Ctrl+S** on your keyboard.

## 5.2 Creating a trait definition

A trait definition allows grouping several attributes into one more complex multi-attribute property. Trait instances can be dynamically added to a type instance as part of the business process when using the application, but they can also be made mandatory as a required trait in a type definition, so that they must always be added when creating a new type instance. For more information on traits (definitions and instances), you can refer to the [Define a namespace, trait and "FILE" document type](#) and [Create instances using custom type with trait](#) sections in the Content Metadata Service (CMS) product documentation or the [Trait](#) resource documentation in the Content Metadata Service API reference.

You can create a trait (i.e.: a trait definition) via any of the three [model creation methods](#). This opens the trait modeler (see Fig. 5.5).

Fig. 5.5:

The screenshot shows the 'Trait Definition Modeler' interface. At the top, there are three input fields: 'Namespace' (a dropdown menu), '\* Display name' (containing 'My Trait'), and '\* Name' (containing 'my\_trait'). Below these is a large text area for 'Description'. Underneath the description is a tabbed interface with 'Attributes' selected. The 'Attributes' tab shows a table with columns: '\* Display name', '\* Name', '\* Data type', 'Default value', 'Size', 'Repe...', 'Requ...', 'Unique', 'Read...', 'Sear...', and 'Sorta...'. The table is currently empty, and a message at the bottom states 'There are currently no attributes to display.'

The different model properties on the trait definition modeler screen are:

- **Namespace:** the namespace to which the trait belongs; the namespace dropdown list is populated with the namespaces that exist within the project, and you can opt not to select any namespace
- **Display name:** the user-friendly name (i.e.: label) of the trait; this does not have to be unique, and a default value is automatically filled using the model name you initially chose
- **Name:** the (technical) name of the trait; this has to be unique (within your developer tenant), and a default value is automatically filled using the display name
- **Description:** the description of the trait



- **Attributes:** the attributes list defines the different attribute definitions of the trait definition; to add an attribute definition to a trait definition, you need to use the  on the top right of the attributes list; each attribute definition (see Fig. 5.6) has the following properties:
  - **Display name:** the user-friendly name of the attribute; this does not have to be unique, but it is recommended (to avoid confusion)
  - **Name:** the technical name of the attribute; this has to be unique within a trait definition, and it gets automatically populated for your convenience based on the display name you fill
  - **Data type:** the data type of the attribute; this is a pick list (bigint, boolean, date, double, integer, string and uuid)
  - **Default value:** the default value for the attribute (i.e.: the value that gets automatically assigned to the attribute when creating a new instance of the trait); whether it is possible to assign a default value and how to assign it depends on the chosen data type
  - **Size:** the size property only applies to the string data type and can thus only be chosen when picking the string data type; it represents the maximum length constraint for the string attribute
  - **Repeating:** whether or not the attribute is multi-valued (can have multiple values)
  - **Unique:** whether or not the attribute needs to be unique across all instances of the trait
  - **Required:** whether or not the attribute must be filled upon creation
  - **Read-only:** whether or not the attribute can be modified after creation
  - **Searchable:** whether or not the attribute can be filtered against when performing a search
  - **Sortable:** whether or not the attribute can be used to sort a search result

Fig. 5.6:



Display name	Name	Data type	Default value	Size	Repeating	Required	Unique	Read-only	Searchable	Sortable



- **Indexes:** for performance and/or unique constraints reasons, it is possible to create indexes for certain attributes or a combination of attributes; the indexes list defines the different index definitions of the trait definition; to add an index definition to a trait definition, you need to use the  on the top right of the indexes list; each index definition (see Fig. 5.7) has the following properties:
  - **Name:** the name of the index
  - **Columns:** the different columns (i.e.: attributes) to which the index applies
  - **Unique:** whether or not a unique constraint needs to be enforced

Fig. 5.7:



Name	Columns	Unique

To save the trait definition model, select **Save** from the **File** menu, or press **Ctrl+S** on your keyboard.

## 5.3 Creating a type definition

A type definition is the main component for building your application's (custom) data model. A type definition has its own attributes and required traits (i.e.: traits that are always added to the type instance upon creation). A type definition can be of three categories: **object** (i.e.: object with metadata, but no content), **file** (i.e.: document with metadata and content) or **folder** (i.e.: container for subfolders, objects and files). Type definitions also allow for inheritance within the same category (i.e.: base type). For more information on types (definitions and instances), you can refer to the [Define a namespace, trait and "FILE" document type](#) and [Create instances using custom type with trait](#) sections in the Content Metadata Service (CMS) product documentation or the [Type](#) resource documentation in the Content Metadata Service API reference.

You can create a type (i.e.: a type definition) via any of the three [model creation methods](#). This opens the type modeler (see Fig. 5.8).

Fig. 5.8:

The screenshot shows the 'Type Definition Modeler' interface. At the top, there are several input fields: 'Namespace' (a dropdown), 'Display name' (text input with 'My Type'), 'Name' (text input with 'my\_type'), 'Category' (a dropdown), and 'Parent' (a dropdown). Below these is a large text area for 'Description'. Underneath the description is a tabbed interface with three tabs: 'Attributes', 'Required traits', and 'Indexes'. The 'Attributes' tab is active, showing a table with the following columns: 'Display name', 'Name', 'Data type', 'Default value', 'Size', 'Repeating', 'Required', 'Unique', 'Read-only', 'Searchable', and 'Sortable'. The table is currently empty, with a message at the bottom stating 'There are currently no attributes to display.'

The different model properties on the type definition modeler screen are:

- **Namespace:** the namespace to which the type belongs; the namespace dropdown list is populated with the namespaces that exist within the project, and you can opt not to select any namespace
- **Display name:** the user-friendly name (i.e.: label) of the type; this does not have to be unique, and a default value is automatically filled using the file name you initially chose
- **Name:** the (technical) name of the type; this has to be unique (within your developer tenant), and a default value is automatically filled using the display name
- **Category:** the type category to which the type belongs; this can be **object**, **file** or **folder**
- **Parent:** the parent type for the type, if it is a subtype of another; the parent dropdown list is populated with the types of the same category that exist within the project
- **Description:** the description of the type



- **Attributes:** the attributes list defines the different attribute definitions of the type definition; to add an attribute definition to a type definition, you need to use the  on the top right of the attributes list; each attribute definition (see Fig. 5.9) has the following properties:
  - **Display name:** the user-friendly name of the attribute; this does not have to be unique, but this is recommended (to avoid confusion)
  - **Name:** the technical name of the attribute; this has to be unique within a type definition, and it gets automatically populated for your convenience based on the display name you fill
  - **Data type:** the data type of the attribute; this is a pick list (bigint, boolean, date, double, integer, string and uuid)
  - **Default value:** the default value for the attribute (i.e.: the value that gets automatically assigned to the attribute when creating a new instance of the type); whether it is possible to assign a default value and how to assign it depends on the chosen data type
  - **Size:** the size property only applies to the string data type and can thus only be chosen when picking the string data type; it represents the maximum length constraint for the string attribute
  - **Repeating:** whether or not the attribute is multi-valued (can have multiple values)
  - **Unique:** whether or not the attribute needs to be unique across all instances of the type
  - **Required:** whether or not the attribute must be filled upon creation
  - **Read-only:** whether or not the attribute can be modified after creation
  - **Searchable:** whether or not the attribute can be filtered against when performing a search
  - **Sortable:** whether or not the attribute can be used to sort a search result


Fig. 5.9:



Display name	Name	Data type	Default value	Size	Repeating	Required	Unique	Read-only	Searchable	Sortable

- **Required traits:** the required traits list defines the different mandatory traits for the type definition; each required trait definition (see Fig. 5.10) has the following properties:
  - **Instance name:** the name of the required trait instance; this must be unique across the type definition's required traits
  - **Trait name:** the selected trait definition for the required trait instance; the trait name dropdown list is populated with the trait definitions that exist within the project

Fig. 5.10:



Instance name	Trait name	Delete



- **Indexes:** for performance and/or unique constraints reasons, it is possible to create indexes for certain attributes or a combination of attributes; the indexes list defines the different index definitions of the type definition; to add an index definition to a type definition, you need to use the  on the top right of the indexes list; each index definition (see Fig. 5.11) has the following properties:
  - **Name:** the name of the index
  - **Columns:** the different columns (i.e.: attributes) to which the index applies
  - **Unique:** whether or not a unique constraint needs to be enforced

Fig. 5.11:



Name	Columns	Unique
<input type="text"/>	<input type="text"/>	<input type="checkbox"/>


To save the type definition model, select **Save** from the **File** menu, or press **Ctrl+S** on your keyboard.

## 5.4 Creating a workflow definition

A workflow definition represents an executable process model from which process instances will be created. The executable process model is stored as BPMN 2.0 encoded JSON. For more information on Workflow Service process models and process instances, you can refer to the [Workflow Service product documentation](#), the [Workflow Modeler product documentation](#) or the [Workflow Service API reference](#).

You can create a workflow (i.e.: a workflow definition) via any of the three [model creation methods](#). This opens the workflow modeler (see Fig. 5.12).

Fig. 5.12:



For an exhaustive user guide of the workflow modeler, please refer to the [Workflow Modeler product documentation](#).

To save the workflow model, select **Save** from the **File** menu, or press **Ctrl+S** on your keyboard.

## 6 Deploying a project

This chapter describes how to deploy a project (i.e.: the application with its models) to the IMaaS API endpoints in the OpenText™ API Cloud. To be able to deploy a project, you must have [set up your VS Code IMaaS authentication profile](#).

Deploying a project can be done via the **More Actions** menu (see Fig. 6.1) or the workspace (root) folder's contextual menu (see Fig. 6.2) in the **Explorer** view, or via the **Deploy Project** command in the **Command Palette** (see Fig. 6.3).

Fig. 6.1:




Fig. 6.2:




Fig. 6.3:



When deploying your application for the first time, the **Output** view automatically opens and displays the **OT Deployment** output. It contains the tenant ID and (application) API key data. These need to be kept securely, as they are to be used in your project code to authenticate/communicate with the IMaaS APIs in context of your application.

Once deployed, an application corresponding with your IMaaS project can be found in the Console view of your developer organization on **[developer.opentext.com](https://developer.opentext.com)**.

## **7 Using the otcloud Command Line Interface**

COMING SOON

## 8 Contact information

OpenText Corporation  
275 Frank Tompa Drive  
Waterloo, Ontario  
Canada, N2L 0A1

For more information, visit [www.opentext.com](http://www.opentext.com)

**Copyright © 2022 Open Text. All Rights Reserved.**

Trademarks owned by Open Text. One or more patents may cover this product. For more information, please visit <https://www.opentext.com/patents>.

### **Disclaimer**

#### **No Warranties and Limitation of Liability**

Every effort has been made to ensure the accuracy of the features and techniques presented in this publication. However, Open Text Corporation and its affiliates accept no responsibility and offer no warranty whether expressed or implied, for the accuracy of this publication.